

ftrobopy - control of the fischertechnik TXT controller in Python

ftrobopy - ftrobopy

```
class ftrobopy.ftrobopy(host = '127.0.0.1', port = 65000, update_interval = 0.01,
special_connection = '127.0.0.1')
```

Extension of the class ftrobopy.ftTXT. In this class, various fischertechnik elements are made available to the end user on a higher level of abstraction (similar to the program elements from the ROBOPRO software). The following program elements are currently implemented:

- **engine**, to control the motor outputs M1-M4
- **output**, to control the universal outputs O1-O8
- **input**, for reading in values from inputs I1-I8
- **resistor**, for measuring an ohmic resistance
- **ultrasonic**, to determine distances with the help of the ultrasound module
- **voltage** to measure a voltage
- **colorsensor** to query the fischertechnik color sensor
- **trailfollower**, to query the fischertechnik track sensor
- **joystick**, to query a joystick of a fischertechnik IR remote control (BT remote control only possible with cfw > 0.9.4)
- **joybutton** to query a button on a fischertechnik IR remote control
- **joydipswitch**, to query the DIP switch setting of an IR remote control

In addition, the following sound routines are available:

- **play_sound**
- **stop_sound**
- **sound_finished**

Initialization of the ftrobopy class:

- Establishing the socket connection to the TXT controller using the base class ftTXT and querying the device name and the firmware version number
- Initialization of all data fields of the ftTXT class with default values and setting of all outputs of the TXT to 0
- Starting a Python background thread that maintains communication with the TXT

Parameter: host (*string*) - Host name or IP number of the TXT module

- 'auto' will automatically find the appropriate mode.
- '127.0.0.1' or 'localhost' automatically use the direct or socket mode, depending on whether the TxtControl Main process is active or not.
- '192.168.7.2' in USB offline mode
- '192.168.8.2' in WLAN offline mode
- '192.168.9.2' in Bluetooth offline mode
- 'direct' in serial online operation with direct control of the motor board of the TXT

Parameter: port (*integrity*) - port number (usually 65000)

- **update_interval** - Time (in seconds) between two calls to the data exchange process with the TXT
- **special_connection** (*string*) - IP address of the TXT, if it is addressed via a router in the WLAN network (e.g. '10.0.2.7')

Return: Empty

Application example:

```
>>> import ftrobopy
>>> ftrob = ftrobopy.ftrobopy('automobile')
```

colorsensor(*num, wait = True*)

This function generates an analog input object to query the fischertechnik color sensor. The color sensor is a photo transistor that measures the light from a red light source reflected from a surface. The distance between the color sensor and the surface to be determined should be between 5mm and 10mm. The colors 'white', 'red' and 'blue' can be reliably differentiated with this method.

The measured value returned is the voltage applied to the phototransistor in mV. The colorsensor () function is basically identical to the voltage () function.

The color sensor object created in this way has the following methods:

value ()

With this method, the applied voltage (in mV) is queried.

Parameter: **num** (*integrity*) - Number of the input to which the sensor is connected (1 to 8)

Return: The recognized color value as an integer number

Return type: integer

color ()

With this method the recognized color is returned as a word.

Return: The recognized color

Return type: string

Application example:

```
>>> color sensor = txt.colorsensor (5)
>>> print("The color value is          : ", color sensor.value ())
>>> print("The recognized color is:", color sensor.color ())
```

input(*num, wait = True*)

This function creates a digital (on / off) input object at one of the inputs I1-I8. This can be, for example, a button, a photo transistor or a reed contact.

Application example:

```
>>> Button = ftrob.input (5)
```

The button input object created in this way has the following methods:

state ()

This method is used to query the status of the digital input.

Parameter: **num** (*integrity*) - Number of the input to which the button is connected (1 to 8)

Return: State of the input (0: contact closed, i.e. input connected to ground, 1: contact open)

Return type: integrity

Application example:

```
>>> if Button.state () == 1:  
    print ("The button at input I5 was pressed.")
```

joybutton(*buttonnum, remote_number = 0, remote_type = 0*)

This function generates an input object to query a button on a fischertechnik IR remote control. The function can only be used meaningfully with the IR remote controls. The blue BT remote control does not transmit the button signals.

Parameter: buttonnum - Number of the button to be queried.

- 0: left button (ON) 1:
- right button (OFF)

Parameter: remote_number - (optional parameter) Number of the IR remote control.

Up to 4 fischertechnik IR remote controls can be queried at the same time, which are differentiated from one another via their DIP switch settings:

- OFF OFF: Number 1
- ON OFF: Number 2
- OFF ON: Number 3
- ON ON: Number 4

If the parameter `remote_number = 0` is set, each of the 4 possible remote controls can be queried, regardless of their DIP switch settings. This is the default setting if the parameter is not specified.

Parameter: remote_type - 0: (red) IR infrared remote control, 1: (blue) BT Bluetooth remote control

This parameter is only available for reasons of compatibility. The BT remote control does not transmit any button signals.

Application example:

```
>>> buttonON      = ftrob.joybutton (0) ftrob.  
>>> buttonOFF     = joybutton (1)  
>>> buttonOFF_2 = ftrob.joybutton (0, 4th) # left (ON) button, the remote control
```

The button object created in this way has the following method:

pressed ()

This method asks whether the button is pressed. Note: In the case of the BT remote control, the value `False` is always returned here.

Return: `False` (= button is not pressed) or `True` (= button is pressed)

Return type: boolean

Application example:

```
>>> button1 = ftrob.joybutton (0) # left (ON) button of a bel. IR remote control
>>> while not button1.pressed ():
>>>     time.sleep (0.1)
>>> print("Button ON was pressed")
```

joydipswitch(remote_type = 0)

This function generates an input object to query the DIP switch of a fischertechnik IR remote control. The function can only be used meaningfully with the IR remote controls. The blue BT remote control has no DIP switches.

Parameter: **remote_type** - 0: (red) IR infrared remote control, 1: (blue) BT Bluetooth remote control

This parameter is only available for reasons of compatibility. The BT remote control has no DIP switches.

Application example:

```
>>> IR_DipSchalter = ftrob.joydipswitch ()
```

The button object created in this way has the following method:

setting ()

This method is used to query the DIP switch setting:

- OFF OFF = 0
- ON OFF = 1
- OFF ON = 2
- ON ON = 3

Return: Value of the DIP switch (0-3). The return value when using the BT remote control is always 0 here.

Return type: integrity

Application example:

```
>>> IR_DipSchalter = ftrob.joydipswitch ()
>>> print("The current setting of the DIP switch is:", IR_DipSchalter.se
```

joystick(joynum, remote_number = 0, remote_type = 0)

This function generates an input object for querying a joystick of a fischertechnik IR remote control.

Parameter: joynum - Number of the joystick to be queried.

- 0: left joystick
- 1: right joystick

Parameter: remote_number - (optional parameter) Number of the IR remote control.

Up to 4 fischertechnik IR remote controls can be queried at the same time, which are differentiated from one another via their DIP switch settings:

- OFF OFF: Number 1
- ON OFF: Number 2
- OFF ON: Number 3
- ON ON: Number 4

If the parameter `remote_number = 0` is set, each of the 4 possible remote controls can be queried, regardless of their DIP switch settings. This is the default setting if the parameter is not specified.

Parameter: **remote_type** - 0: (red) IR infrared remote control, 1: (blue) BT Bluetooth remote control

Notes on the BT remote control:

- The BT remote control can currently only be used with the community firmware (cfw version > 0.9.4) in offline mode (direct).
- Before the BT remote control can be used, the `ft_bt_server` process must first be started. This can be done on the TXT command line with the command: **sudo ft_bt_server** can be achieved. Alternatively, the `ft_bt_server` process can also be used via the cfw app **LNT BT server** can be started via the touchscreen of the TXT. Only one
- BT remote control can be queried. The parameter: `param remote_number:` is then automatically set to 0.
- The buttons of the blue BT remote control are not transmitted by this and can therefore not be queried.
- Internally, the BT remote control has twice the (integer) resolution [-30 ... +30] of the IR remote control [-15 ... +15]. Both value ranges are set to the (float) range [-1.0 ... +1.0] mapped.

Attention new: the mapping to the value range [-1.0 ... +1.0] has only existed since `ftrobopy` version 1.86. In the previous versions the (integer) range [-15 ... +15] was returned.

A total of 4 different IR and a BT remote control can be queried at the same time on a TXT.

Application example:

```
>>> joystick links          = ftrob.joystick(0)= ftrob.          # left joystick all 4 pos          /
>>> joystick right         joystick(1)= ftrob.joystick(0, 2)    # right joystick of all 4 moe      G
>>> joystick number 3      # left joystick of the IR remote      e
>>> joystickBlueLeft       = ftrob.joystick(0, 0, 1) # left joystick of the BT remote control e
>>> joystickBlueRight = ftrob.joystick(0, 0, 1) # left joystick of the BT remote control e
```

The joystick object created in this way has the following methods:

isConnected ()

This method can be used to test whether a joystick is connected to the TXT via Bluetooth and whether the query thread is running. For IR joysticks this is always true, since IR joysticks do not have to be connected separately (the TXT always listens to the IR LED to see whether a signal is being received).

Return: True or False

Application example:

```
>>> joy1 = txt.joystick(0,0,1) # 1 = BT joystick
>>> joy2 = txt.joystick(0,0,0) # 0 = IR joystick
```

```
>>> if joy1.isConnected ():
>>>     print("A Bluetooth joystick is connected.")
>>> if joy2.isConnected (): # for IR joysticks this value is always true
>>>     print("An IR joystick is connected")
```

leftright ()

This method queries the horizontal (left-right) axis.

Return: - 1.0 (joystick all the way to the left) to +1.0 (joystick all the way to the right), 0: middle position

updown ()

With this method the vertical (up-down) axis is queried.

Return: - 1.0 (joystick all the way down) to +1.0 (joystick all the way up), 0: middle position

Application example:

```
>>> joystick1 = ftrob.joystick(0) # left joystick one bel. IR remote control
>>> print("Left-right position =", joystick1.leftright (), "Up-Down-Stellu
```

engine(output, wait = True)

This function creates a motor object that is used to control a motor that is connected to one of the motor outputs M1-M4 of the TXT. If the high-speed counters C1-C4 are also connected (e.g. through the use of encoder motors or counting wheels), axis revolutions can also be measured precisely and thus distances covered can be determined. In addition, two motor outputs can be synchronized with each other, for example to achieve perfect straight-line stability with robot models.

Application example:

```
>>> Motor1 = ftrob.engine(1)
```

The motor object created in this way has the following functions:

- **setSpeed (speed)**
- **setDistance (distance, syncto = None)**
- **finished ()**
- **getCurrentDistance ()**
- **stop()**

The functions in detail:

setSpeed (speed)

Adjustment of the motor speed

Parameter: **speed** (*integrity*) -

Return: Empty

Specifies the speed at which the motor should run:

- the speed range is between 0 (stop motor) and 512 (maximum speed)

- If the speed is negative, the motor runs backwards

Note: The entered value for the speed does not depend linearly on the actual one

Rotational speed of the motor combined, ie the speed 400 is not twice as high as the speed 200. With higher values of speed, the speed can be regulated in finer steps.

Application example:

```
>>> Motor1.setSpeed (512)
```

Let the engine run at maximum speed.

setDistance (distance, syncto = None)

Setting of the motor distance, which is measured by the fast counter, which of course has to be connected.

- Parameter:**
- **distance** (*integrity*) - Indicates how many counter counts the motor should turn (the encoder motor gives 72 pulses per axis revolution)
 - **syncto** (*ftrobopy.motor object*) - This can be used to synchronize two motors, for example to enable perfect straight-line stability. The motor object to be synchronized is transferred here as a parameter.

Return: Empty

Application example:

The motor at connection M1 is synchronized with the motor at connection M2. The motors M1 and M2 run until both motors have reached the set distance (axis revolutions / 72). If one or both motors are not connected to the fast counter inputs, the motors will run until the Python program is terminated!

```
>>> Engine_links=ftrob.engine(1)
>>> Motor_right=ftrob.engine(2)
>>> Motor_links.setDistance (100,          syncto=Motor_right)
>>> Engine_right.setDistance (100,          syncto=Motor_links)
```

finished ()

Query whether the set distance has already been reached.

Return: False: Motor is still running, True: Distance reached

Return type: boolean

Application example:

```
>>> while not Motor1.finished ():print
      ("engine is still running")
```

getCurrentDistance ()

Query of the distance that the motor has covered since the last setDistance command.

Return: Current value of the motor counter

Return type: integer

stop ()

Stopping the motor by setting the speed to 0.

Return: Empty

Application example:

```
>>> Motor1.stop()
```

output(num, level = 0, wait = True)

This function creates a general output object that is used to control elements that are connected to outputs O1-O8.

Application example:

A lamp or an LED is connected to output O7:

```
>>> lamp = ftrob.output(7th)
```

The general output object generated in this way has the following methods:

setLevel (level)

Parameter: **level** (*integer, 1 - 512*) - Output power that should be applied to the output (more precisely for the experts: the total length of the working interval of a PWM cycle in units of 1/512, ie with level = 512 the PWM signal is high during the entire cycle).

This method can be used to set the output power, for example to regulate the brightness of a lamp.

Application example:

```
>>> lamp.setLevel (512)
```

play_sound(idx, repeat = 1, volume = 100)

Play a sound one or more times.

- 0: No sound (= stop sound output) 1:
- Airplane
- 2: alarm
- 3: bell
- 4: brakes
- 5: car horn (short) 6:
- car horn (long) 7:
- breaking wood 8:
- excavator
- 9: Fantasy 1
- 10: Fantasy 2
- 11: Fantasy 3
- 12: Fantasy 4
- 13: farm
- 14: Fire brigade siren
- 15: fireplace
- 16: Formula 1 car

- 17: helicopter
- 18: Hydraulics
- 19: Running engine 20:
- Starting engine 21:
- Propeller plane 22:
- Roller coaster
- 23: Ship's horn
- 24: tractor
- 25: truck
- 26: wink
- 27: Driving noise
- 28: lift your head
- 29: Tilt your head

Parameter:

- **idx** (*integrity*) - number of the sound
- **repeat** (*integrity*) - Number of repetitions (default = 1)
- **volume** (*integrity*) - Volume with which the sound is played (0 = not audible, 100 = maximum volume, default = 100). The volume can only be changed in 'direct' mode.

Return: Empty

Application example:

```
>>> ftrob.play_sound (27, 5) # Play the driving noise 5 times in a row
>>> ftrob.play_sound (5, repeat=2, volume=10) # Horn softly twice in a row
```

resistor(*num, wait = True*)

This function creates an analog input object to query a resistor that is connected to one of the inputs I1-I8. This can be, for example, a temperature-dependent resistor (NTC resistor) or a photoresistor.

Application example:

```
>>> R. = ftrob.resistor (7th)
```

The resistance object created in this way has the following methods:

value ()

With this method the resistance is queried.

Parameter: **num** (*integrity*) - Number of the input to which the resistor is connected (1 to 8)

Return: The resistance value at the input in ohms for resistors up to 15kOhm, for higher resistance values is always returned 15000

Return type: *integrity*

Application example:

```
>>> print("The resistance is", R.value ())
```

ntcTemperature ()

With this method, the temperature of the fischertechnik NTC resistor is queried.

Return: The temperature of the resistor connected to the input in degrees

Celsius.

Return type: float

Application example:

```
>>> print("The temperature of the fischertechnik NTC resistor is", R.ntcT
```

e

sound_finished()

Check whether the last played sound has already expired

Return: True (sound is ready) or False (sound is still playing)

Return type: boolean

Application example:

```
>>> while not ftrob.sound_finished ():passport
```

stop_sound()

Stop the current sound output. The sound index to be played is set to 0 (= no sound) and the value for the number of repetitions is set to 1.

Return: Empty

Application example:

```
>>> ftrob.stop_sound ()
```

trailfollower(*num*, *wait* = *True*)

This function creates a digital input object to query a track sensor that is connected to one of the inputs I1-I8. (Internally, this function is identical to the voltage () function and measures the applied voltage in mV). From a voltage of 600mV a digital 1 (track is white) is returned, otherwise the value is a digital 0 (track is black). If an analog input value is required for the track sensor, the voltage () function can also be used.

Application example:

```
>>> L. = ftrob.trailfollower (7th)
```

The sensor object created in this way has the following methods:

state ()

With this method the track sensor is queried.

Parameter: **num** (*integrity*) - Number of the input to which the sensor is connected (1 to 8)

Return: The value of the track sensor (0 or 1) connected to the input.

Return type: integrity

Application example:

```
>>> print("The value of the track sensor is", L.state ())
```

ultrasonic(*num*, *wait* = *True*)

This function creates an object to query a TX / TXT ultrasonic distance meter connected to one of the inputs I1-I8.

Application example:

```
>>> ultrasonic = ftrob.ultrasonic (6th)
```

The ultrasonic object generated in this way has the following methods:

distance ()

With this method, the current distance value is queried

Parameter: **num** (*integrity*) - Number of the input to which the ultrasonic distance meter is connected (1 to 8)

Return: The current distance between the ultrasonic sensor and the object in front of it in cm.

Return type: integrity

Application example:

```
>>> print("The distance to the wall is", ultrasound.distance (), "cm.")
```

voltage(*num, wait = True*)

This function creates an analog input object to query the voltage level that is connected to one of the inputs I1-I8. In this way, for example, the charge status of the battery can also be monitored. The fischertechnik color sensor can also be queried with this object.

Application example:

```
>>> battery = ftrob.voltage (7th)
```

The voltage measurement object created in this way has the following methods:

voltage ()

With this method, the applied voltage (in mV) is queried. Voltages in the range from 5mV to 10V can be measured. If the applied voltage is greater than 600mV, the digital value for this input is also set to 1.

Parameter: **num** (*integrity*) - Number of the input to which the voltage source (e.g. battery) is connected (1 to 8)

Return: The voltage present at the input (in mV)

Return type: integer

Application example:

```
>>> print("The tension is", battery.voltage (), "mV")
```

ftrobopy - ftTXT base class

```
class ftrobopy.ftTXT(host = '127.0.0.1', port = 65000, serport = '/ dev / ttyO2', on_error = <function  
default_error_handler>, on_data = <function default_data_handler>, directmode = False)
```

Basic class for the fischertechnik TXT computer. Implements the protocol for data exchange via Unix sockets. The methods of this class are typically not called directly by the end user, but only indirectly via the methods of the class `ftrobopy.ftrobopy`, which is an extension of the class `ftrobopy.ftTXTBase`.

The following constants are defined in the class:

- `C_VOLTAGE` = 0 *To use an input as a voltmeter*
- `C_SWITCH` = 1 *To use an input as a button*
- `C_RESISTOR` = 1 *To use an input as a resistor, e.g. Photoresistor*
- `C_ULTRASONIC` = 3 *To use an input as a distance meter*
- `C_ANALOG` = 0 *The input is used analog*
- `C_DIGITAL` = 1 *Input is used digitally*
- `C_OUTPUT` = 0 *Output (O1-O8) is used to control a lamp, for example used*
- `C_MOTOR` = 1 *Output (M1-M4) is used to control a motor used*

Initialization of the `ftTXT` class:

- All outputs are set to 1 (= motor) by default
- All inputs are set to 1, 0 (= button, digital) by default. All
- counters are set to 0

Parameter: `host` (*string*) - Host name or IP number of the TXT module

- '127.0.0.1' in download mode
- '192.168.7.2' in USB offline mode
- '192.168.8.2' in WLAN offline mode
- '192.168.9.2' in Bluetooth offline mode

Parameter:

- **`port`** (*function (str, exception) -> bool*) - port number (usually 65000)
- **`serport`** (*string*) - Serial port for direct control of the motor board of the TXT
- **`on_error`** - Error handler for errors in communication with the controller (optional)

Return: Empty

Application example:

```
>>> import ftrobopy
>>> txt = ftrobopy.ftTXT ('192.168.7.2', 65000)
```

SyncDataBegin()

The functions `SyncDataBegin ()` and `SyncDataEnd ()` are used to execute a whole group of commands at the same time.

Application example:

The three outputs `motor1`, `motor2` and `lamp1` are activated at the same time.

```
>>> SyncDataBegin ()
>>> engine1.setSpeed (512)
>>> engine2.setSpeed (512)
>>> lamp1.setLevel (512)
>>> SyncDataEnd ()
```

SyncDataEnd()

The functions SyncDataBegin () and SyncDataEnd () are used to execute a whole group of commands at the same time.

Application example see SyncDataBegin ()

cameraOnline()

This command can be used to query whether the camera process has been started

Return:

Return type: boolean

getCameraFrame()

This function returns the current camera image of the TXT (in jpeg format). The camera process on the TXT must have been started beforehand.

Application example:

```
>>> pic = txt.getCameraFrame ()
```

Return: jpeg image

getConfig()

Query the current configuration of the TXT

Return: M [4], I [8] [2]

Return type: M: int [4], I: int [8] [2]

Application example: Change of input I2 to analog ultrasonic distance measurement

- Note: In Python, field elements are typically addressed using the indices 0 to N-1
- The input I2 of the TXT is addressed in this example via the field element I [1]

```
>>> M, I = txt.getConfig ()
>>> I [1] = (txt.C_ULTRASONIC, txt.C_ANALOG)
>>> txt.setConfig (M, I) txt.
>>> updateConfig ()
```

getCounterCmdId(*idx = None*)

Returns the last Counter Command ID of a (fast) counter

Parameter: **idx** - Number of the counter. (Note: the count is from 0 to 3 for counters C1 to C4)

Application example:

Read the counter command ID of the fast counter C3 into variable num.

```
>>> num = txt.getCounterCmdId (2)
```

getCurrentCounterCmdId(*idx = None*)

Returns the current counter command ID of one or all counters.

Parameter: **idx** (*integrity*) - number of the counter

Return: Current command ID of a counter (idx = 0-3) or all counters of the TXT controller as an array [4] (idx = None or no idx specified)

Note:

- the idx parameter is specified from 0 to 3 for counters C1 to C4.

Application example:

```
>>> cid = txt.getCurrentCounterCmdId (3)
>>> print("Current Counter Command ID from C4:", cid)
```

getCurrentCounterInput(*idx = None*)

Shows whether a counter or all counters (as an array [4]) have changed since the last query.

Parameter: **idx** (*integrity*) - number of the counter

Return: Current status value of a counter (idx = 0-3) or all fast counters of the TXT controller as an array [4] (idx = None or no idx specified)

Note:

- the idx parameter is specified from 0 to 3 for counters C1 to C4.

Application example:

```
>>> c = txt.getCurrentCounterInput (0)
>>> if c==0:
>>>     print("Counter C1 has not changed since the last query")else:
>>>
>>>     print("Counter C1 has changed since the last query")
```

getCurrentCounterValue(*idx = None*)

Returns the current value of one or all fast counter inputs. This can be used, for example, to check how far an engine has already driven.

Parameter: **idx** (*integrity*) - number of the counter

Return: Current value of a counter (idx = 0-3) or all fast counters of the TXT controller as an array [4] (idx = None or no idx specified)

Note:

- the idx parameter is specified from 0 to 3 for counters C1 to C4.

Application example:

```
>>> print("Current value of C1:", txt.getCurrentCounterValue (0))
```

getCurrentInput(*idx = None*)

Returns the current value of an input or all inputs returned by the TXT as an array

Parameter: **idx** (*integrity*) - number of the input

Return: Current value of an input (idx = 0-7) or all current input values of the TXT controller as an array [8] (idx = None or no idx specified)

Note:

- the idx parameter is specified from 0 to 7 for inputs I1 to I8.

Application example:

```
>>> print("The current value of input I4 is:", txt.getCurrentInput (3))
```

getCurrentIr()

Returns a list with the current values of the IR remote control (no direct mode support). This function is obsolete and should no longer be used.

getCurrentMotorCmdId(*idx = None*)

Returns the current Motor Command ID of one or all motors.

Parameter: *idx (integrity)* - number of the engine

Return: Current command ID of a motor (*idx* = 0-3) or all motors of the TXT controller as an array [4] (*idx* = None or no *idx* specified)

Note:

- the *idx* parameter is specified from 0 to 3 for motors M1 to M4.

Application example:

```
>>> print("Current Motor Command ID of M4:", txt.getCurrentMotorCmdId (3))
```

getCurrentSoundCmdId()

Returns the current Sound Command ID.

Return: The current Sound Command ID

Return type: integer

Application example:

```
>>> print("The current Sound Command ID is:", txt.getCurrentSoundCmdId ())
```

getDevicename()

Returns the name of the TXT previously read out with `queryStatus ()`

Return: Device name (string)

Application example:

```
>>> print('Name of the TXT:', txt.getDevicename ())
```

getExtensionPower()

Provides the current voltage in mV that is applied to the extension bus.

This function is only available in 'direct' mode.

Application example:

```
>>> Extension tension = txt.getExtensionPower ()
```

getFirmwareVersion()

Returns the version number previously read out with `queryStatus ()` as a string.

Return: Firmware version number (str)

Application example:

```
>>> print(txt.getFirmwareVersion ())
```

getHost()

Returns the current network setting (typically the IP address of the TXT). : return:
host address: rtype: string

getMotorCmdId(*idx = None*)

Returns the last Motor Command ID of a motor output (or all motor outputs as an array).

Parameter: **idx** (*integrity*) - Number of the motor output. If this parameter is not specified, the Motor Command ID of all motor outputs is returned as an array [4].

Return: The Motor Command ID of one or all of the motor outputs

Return type: integer or integer [4] array

Application example:

```
>>> last_cmd_id = txt.getMotorCmdId (4th)
```

getMotorDistance(*idx = None*)

Returns the last set motor distance for one or all motor outputs.

Parameter: **idx** (*integrity*) - Number of the motor output

Return: Last set distance of a motor (idx = 0-3) or all last set distances (idx = None or no idx parameter specified)

Note:

- the idx parameter is specified from 0 to 3 for the motor outputs M1 to M4.

Application example:

```
>>> md = txt.getMotorDistance (1)
>>> print("Distance set for M2 with setMotorDistance ():", md)
```

getMotorSyncMaster(*idx = None*)

Returns the last set configuration of the motor synchronization for one or all motors.

Parameter: **idx** (*integrity*) - The number of the motor whose synchronization is to be delivered or None or <empty> for all outputs.

Return: Empty

Note:

- the idx parameter is specified from 0 to 3 for the motor outputs M1 to M4.
- or None or <empty> for all motor outputs.

Application example:

```
>>> xm = txt.getMotorSyncMaster ()
```

```
>>> print("Current configuration of all motor synchronizations:", xm)
```

getPort()

Returns the current network port to the TXT (usually 65000). : return: network port: rtype: int

getPower()

Provides the current voltage of the connected power supply of the TXT in mV (power supply or battery voltage).

This function is only available in 'direct' mode.

Application example:

```
>>> tension = txt.getPower ()
>>> if tension < 7900:
>>>     print("Warning: the battery voltage of the TXT is low. The battery, please
```

getPwm(*idx = None*)

Returns the last set values of the outputs O1-O8 (as array [8]) or the value of an output.

Parameter: idx (*integer or None, or empty*) -

- If no idx parameter was specified, all Pwm settings are returned as array [8].
- Otherwise only the Pwm value of the output specified with idx is returned.

Note: the idx parameter is specified from 0 to 7 for the outputs O1-O8

Return: the output O1 to O8 specified by (idx + 1) or the entire Pwm array

Return type: integer or integer array [8]

Application example:

Delivers the

```
>>> M1_a = txt.getPwm (0)
>>> M1_b = txt.getPwm (1)
>>> if M1_a > 0 other M1_b == 0:
    print ("Speed motor M1:", M1_a, "(forward).") else:
    if M1_a == 0 and M1_b > 0:
        print ("Speed motor M1:", M1_b, "(backwards).")
```

getReferencePower()

Provides the current reference voltage in mV.

This function is only available in 'direct' mode.

Application example:

```
>>> Reference voltage = txt.getReferencePower ()
```

getSoundCmdId()

Returns the last Sound Command ID.

Return: Last Sound Command ID

Return type: integer

Application example:

```
>>> last_sound_cmd_id = txt.getSoundCmdId ()
```

getSoundIndex()

Returns the number of the currently set sound.

Return: Number of the currently set sound

Return type: integer

Application example:

```
>>> current_sound = txt.getSoundIndex ()
```

getSoundRepeat()

Returns the currently set number of repetitions of the sound.

Return: Currently set number of repetitions of the sound.

Return type: integrity

Application example:

```
>>> repeat_rate = txt.getSoundRepeat ()
```

getSoundVolume()

Returns the current volume at which sounds are played.

Return: 0 = not audible up to 100 = full volume

Return type: integer

This function is only available in 'direct' mode.

Application example:

```
>>> v=txt.getSoundVolume (50)
>>> print("Currently set sound volume =", v)
```

getTemperature()

Returns the current temperature of the CPU of the TXT (unit:?).

This function is only available in 'direct' mode.

Application example:

```
>>> temperature = txt.getTemperature ()
>>> print("The temperature inside the TXT is:", Temperature, " (Unit
```

getVersionNumber()

Returns the version number previously read out with queryStatus (). In order to be able to read off the firmware version directly, this number has to be converted into a hexadecimal value

Return: Version number (integer)

Application example:

```
>>> print(hex(txt.getVersionNumber ()))
```

i2c_read(*dev*, *reg*, *reg_len* = 1, *data_len* = 1, *debug* = False)

Read I2C

- Parameter:**
- **dev** (*integrity*) - The I2C device address
 - **reg** (*integrity*) - The register that is to be read out (subdevice address)
 - **reg_len** (*integrity*) - The length of the register in bytes (default = 1)
 - **data_len** (*integrity*) - The length of the data response (default = 1)

Return: The data response of the I2C device (string)

Application example:

```
>>> res=txt.i2c_read (0x18, 0x3f, data_len=6th)
>>> x, y, z=struct.unpack ('<hhh', res)
>>> print("Acceleration of the BMX055 combi sensor in x, y and z directions =",
```

i2c_write(*dev*, *reg*, *value*, *debug* = False)

I2C write

- Parameter:**
- **dev** (*integrity*) - The I2C device address
 - **reg** (*integrity*) - The register to be written to (subdevice address)
 - **value** (*integer (0-255)*) - The value to be written to the register

Return: True (boolean) for error-free execution, otherwise "None"

Application example:

```
>>> # Settings for BMX055 acceleration
>>> txt.i2c_write (0x18, 0x3e, 0x80)
>>> txt.i2c_write (0x18, 0x0f, 0x0c)
>>> txt.i2c_write (0x18, 0x10, 0x0f)
```

incrCounterCmdId(*idx*)

The Counter Command ID is increased by one. If the counter command ID of a counter is increased by one, the corresponding counter is reset to 0.

- Parameter:** **idx** (*integrity*) - Number of the fast counter input whose Command ID is to be increased. (Note: the count is from 0 to 3 for counters C1 to C4)

Return: Empty

Application example:

The Counter Command ID of Counter C4 is increased by one.

```
>>> txt.incrCounterCmdId (3)
```

incrMotorCmdId(*idx*)

The so-called Motor Command ID is increased by 1.

This method must always be called when the distance setting of a motor (measured via the 4 fast counter inputs) has been changed or when a motor is to be synchronized with another motor. If only the motor speed was changed, calling the `incrMotorCmdId ()` method is not necessary.

Parameter: idx (*integrity*) - Number of the motor output

Attention:

- The count is from 0 to 3, idx = 0 corresponds to motor output M1 and idx = 3 corresponds to motor output M4

Application example:

The motor that is connected to the TXT connection M2 should cover a distance of 200 (counter counts).

```
>>> txt.setMotorDistance (1, 200) txt.  
>>> incrMotorCmdId (1)
```

incrSoundCmdId()

The Sound Command ID is increased by one. The Sound Command ID must always be increased by one if a new sound is to be played or if the number of repetitions of a sound has been changed. If no new sound index was selected and the repetition rate was not changed, the current sound will be played again.

Return: Empty

Application example:

```
>>> txt.incrSoundCmdId ()
```

queryStatus()

Query of the device name and the firmware version number of the TXT After converting the version number into a hexadecimal value, the version can be read off directly.

Return: Device name (string), version number (integer)

Application example:

```
>>> name, version = txt.queryStatus ()
```

setConfig(M., I.)

Setting the configuration of the inputs and outputs of the TXT. This function only sets the corresponding values in the `ftTXT` class. The `updateConfig` method is used to transfer the values to the TXT.

Parameter: M. (*int [4]*) - Configuration of the 4 motor outputs (0 = simple output, 1 = motor output)

- Value = 0: Use of the two outputs as simple outputs
- Value = 1: Use of the two outputs as motor output (left-right run)

Parameter: I. (*int [8] [2]*) - Configuration of the 8 inputs

Return: Empty

Application example:

- Configuration of outputs M1 and M2 as motor outputs
- Configuration of outputs O5 / O6 and O7 / O8 as simple outputs
- Configuration of inputs I1, I2, I6, I7, I8 as buttons
- Configuration of input I3 as an ultrasonic distance meter
- Configuration of input I4 as an analog voltmeter
- Configuration of input I5 as an analog ohmmeter

```
>>> M. = [txt.C_MOTOR, txt.C_MOTOR, txt.C_OUTPUT, txt.C_OUTPUT]
>>> I. = [(txt.C_SWITCH,          txt.C_DIGITAL),
          (txt.C_SWITCH,          txt.C_DIGITAL),
          (txt.C_ULTRASONIC,      txt.C_ANALOG),
          (txt.C_VOLTAGE,         txt.C_ANALOG),
          (txt.C_RESISTOR,        txt.C_ANALOG),
          (txt.C_SWITCH,          txt.C_DIGITAL),
          (txt.C_SWITCH,          txt.C_DIGITAL),
          (txt.C_SWITCH,          txt.C_DIGITAL)]
>>> txt.setConfig (M, I) txt.
>>> updateConfig ()
```

setMotorDistance(*idx, value*)

This can be used to set the distance (as a number of fast counter counts) for a motor.

Parameter: **idx** (*integrity*) - Number of the engine output

Return: Empty

Note:

- the idx parameter is specified from 0 to 3 for the motor outputs M1 to M4.

Application example:

The motor at output M3 should turn 100 counter counts. To complete the distance command, the MotorCmdId of the motor must also be increased.

```
>>> txt.setMotorDistance (2, 100) txt.
>>> incrMotorCmdId (2)
```

setMotorSyncMaster(*idx, value*)

This allows two motors to be synchronized with each other, e.g. for perfect straight-line stability.

Parameter: • **idx** (*integrity*) - The motor output to be synchronized
 • **value** (*integrity*) - The number of the motor output to be used for synchronization.

Return: Empty

Note:

- the idx parameter is specified from 0 to 3 for the motor outputs M1 to M4. the value
- parameter is specified from 1 to 4 for the motor outputs M1 to M4.

Application example:

The motor outputs M1 and M2 are synchronized. To complete the synchronization commands, the MotorCmdId of the motors must also be increased.

```
>>> txt.setMotorSyncMaster (0, txt. 2)
>>> setMotorSyncMaster (1, txt. 1)
>>> incrMotorCmdId (0) txt.
>>> incrMotorCmdId (1)
```

setPwm(*idx*, *value*)

Setting the output value for a motor or output output. Typically, this function is not called directly, but is used by derived classes to set the output values. Exception: with the help of these functions, outputs can be quickly set to 0, e.g. to implement an emergency stop (see also stopAll)

- Parameter:**
- **idx** (*integer (0-7)*) - number of the output. (Note: the number is from 0 to 7 for outputs O1-O8)
 - **value** (*integer (0-512)*) - Value to which the output should be set (0: output switched off, 512: output at maximum)

Return: Empty

Application example:

- The motor at connection M1 should run backwards at full speed. The lamp
- at connection O3 should light up at half its luminosity.

```
>>> txt.setPwm (0,0) txt.
>>> setPwm (1,512) txt.
>>> setPwm (2,256)
```

setSoundIndex(*idx*)

Setting a new sound.

Parameter: **idx** (*integer*) - Number of the new sound (0 = no sound, 1-29 sounds of the TXT)

Return: Empty

Application example:

Set the sound "wink" and play it twice.

```
>>> txt.setSoundIndex (26th) txt.
>>> setSoundRepeat (2) txt.
>>> incrSoundCmdId ()
```

setSoundRepeat(*rep*)

Set the number of times a sound is repeated.

Parameter: **rep** (*integer*) - Number of repetitions (0 = repeat infinitely many times)

Application example:

Play "Motor-Sound" infinitely often (ie until the end of the program or until the next change in the number of repetitions).

```
>>> txt.setSound (19th) # 19 = engine sound
>>> txt.setSoundRepeat (0)
```


setSoundVolume(*volume*)

Sets the volume at which sounds are played.

Parameter: volume - 0 = not audible up to 100 = maximum volume (default = 100).

This function is only available in 'direct' mode.

Application example:

```
>>> txt.setSoundVolume (10)           # Set the volume to 10%
```

startCameraOnline()

Starts the process on the TXT that outputs the current camera image via port 65001 and starts a Python thread that continuously fetches the camera frames from the TXT. The frames are delivered by the TXT in jpeg format. Only the most recent image is saved.

After starting the camera process on the TXT, it takes up to 2 seconds for the first image to be sent by the TXT.

Application example:

Starts the camera process, waits 2.5 seconds and saves the imported image as a 'txtimg.jpg' file.

```
>>> txt.startCameraOnline () time.  
>>> sleep (2.5)  
>>> pic = txt.getCameraFrame ()  
>>> with open('txtimg.jpg','wb') as f:  
>>>     f.write (bytearray(pic))
```

startOnline(*update_interval* = 0.02)

Starts the online operation of the TXT and starts a Python thread that maintains the connection to the TXT.

Return: Empty

Application example:

```
>>> txt.startOnline ()
```

stopAll()

Sets all outputs to 0 and thus stops all motors and switches off all lamps.

Return:

stopCameraOnline()

Kills the local Python camera thread and the camera process on the TXT.

Application example:

```
>>> txt.stopCameraOnline ()
```

stopOnline()

Terminates the online operation of the TXT and terminates the Python thread that was responsible for the data exchange with the TXT.

Return: Empty

Application example:

```
>>> txt.stopOnline ()
```

updateConfig()

Transfer of the configuration data for the inputs and outputs to the TXT

Return: Empty

Application example:

```
>>> txt.setConfig (M, I) txt.  
>>> updateConfig ()
```

updateWait(*minimum_time = 0.001*)

Wait until the next data exchange cycle with the TXT has been successfully completed.

Application example:

```
>>> engine1.setSpeed (512)  
>>> engine1.setDistance (100)  
>>> while not engine1.finished ():  
>>>     txt.updateWait ()
```

A simple “pass” instead of “updateWait ()” would lead to a significantly higher CPU load.